

# Setting up Email Accounts on Your iPhone

Print this Article

Comment on this Article

Last Updated: February 21, 2008 9:14 AM


You can use iTunes to synchronize email accounts to your iPhone that you have set up in Mail and Microsoft Entourage on a Mac or Microsoft Outlook and Outlook Express on a PC.

You can set up and make changes to an email account directly on your iPhone. Your email service provider can give you the account settings you need to enter. However, changes you make on your iPhone to an email account that you synchronized from your computer are not copied to your computer.


**Note:** Synchronizing an email account to your iPhone copies your email account settings, but does not copy your email messages. Whether the messages in your Inbox display on both your iPhone and your computer depends on the type of email account you have and how it is configured.

## Setting Up an Email Account on your iPhone

1. If this is the first email account you're setting up on your iPhone, tap **Mail**. Otherwise, from the Home screen, tap **Settings**.



2. On the Settings screen, tap **Mail**.



3. On the Mail screen, under **Accounts**, tap **Add Account**.



4. On the **Add Account** screen, tap **Other**.
5. Select **POP** and then enter your account information using your keypad.  
**Name**  
Enter your name.

**Address**

Enter your email address.

**Description**

Enter a description of this email address. The description displays in your email account list on your iPhone.

6. Enter your **Incoming Mail Server** information.  
**Host Name**  
Enter **pop.secureserver.net**.

**User Name**

Enter your full email address as your user name.

**Password**

Enter your password for your email account.

7. Enter your **Outgoing Mail Server (SMTP)** information.  
**Host Name**  
Enter **smtpout.secureserver.net**.

If you need to change your port, use one of the following for your outgoing mail server, depending on the port you want to use:

**smtpout.secureserver.net:25**

**smtpout.secureserver.net:80**

**smtpout.secureserver.net:3535**

**User Name**

Enter your full email address as your user name.

**Password**

Enter your password for your email account.

**Note:** The user name and password for your outgoing server is the same as the user name and password your entered for the incoming server.

8. If SSL mode is enabled, under **Outgoing Mail Server (SMTP)**, tap **Advanced**.



Outgoing Mail Server (SMTP)

Host Name smtpout.secureserver.net

User Name mymail@mydomain.com

Password .....

Advanced >

9. Set **Incoming Uses SSL** and **Outgoing Uses SSL** to **OFF**.